Systems of Differential Equations The Eigenanalysis Method

- ullet First Order 2×2 Systems $\mathbf{x}' = A\mathbf{x}$
- ullet First Order 3×3 Systems $\mathbf{x}' = A\mathbf{x}$
- Second Order 3×3 Systems x'' = Ax
- Vector-Matrix Form of the Solution of $\mathbf{x}' = A\mathbf{x}$
- ullet Four Methods for Solving a System $\mathbf{x}' = A\mathbf{x}$

The Eigenanalysis Method for First Order 2 imes 2 Systems

Suppose that A is 2×2 real and has eigenpairs

$$(\lambda_1,\mathrm{v}_1), \quad (\lambda_2,\mathrm{v}_2),$$

with v_1 , v_2 independent. The eigenvalues λ_1 , λ_2 can be both real. Also, they can be a complex conjugate pair $\lambda_1 = \overline{\lambda}_2 = a + ib$ with b > 0.

Theorem 1 (Eigenanalysis Method)

The general solution of x' = Ax is

$$\mathbf{x}(t) = c_1 e^{\lambda_1 t} \mathbf{v}_1 + c_2 e^{\lambda_2 t} \mathbf{v}_2.$$

Solving 2 imes 2 Systems $\mathrm{x}' = A\mathrm{x}$ with Complex Eigenvalues _____

If the eigenvalues are complex conjugates, then the real part w_1 and the imaginary part w_2 of the solution $e^{\lambda_1 t}v_1$ are independent solutions of the differential equation. Then the general solution in *real form* is given by the relation

$$x(t) = c_1 w_1(t) + c_2 w_2(t).$$

The Eigenanalysis Method for First Order 3×3 Systems

Suppose that A is 3×3 real and has eigenpairs

$$(\lambda_1,\mathrm{v}_1), \quad (\lambda_2,\mathrm{v}_2), \quad (\lambda_3,\mathrm{v}_3),$$

with v_1 , v_2 , v_3 independent. The eigenvalues λ_1 , λ_2 , λ_3 can be all real. Also, there can be one real eigenvalue λ_3 and a complex conjugate pair of eigenvalues $\lambda_1 = \overline{\lambda}_2 = a + ib$ with b > 0.

Theorem 2 (Eigenanalysis Method)

The general solution of $\mathbf{x}' = A\mathbf{x}$ with 3×3 real A can be written as

$$x(t) = c_1 e^{\lambda_1 t} v_1 + c_2 e^{\lambda_2 t} v_2 + c_3 e^{\lambda_3 t} v_3.$$

Solving 3×3 Systems x' = Ax with Complex Eigenvalues ____

If there are complex eigenvalues $\lambda_1 = \overline{\lambda}_2$, then the real general solution is expressed in terms of independent solutions

$$w_1 = Re(e^{\lambda_1 t}v_1), \ w_2 = Im(e^{\lambda_1 t}v_1)$$

as the linear combination

$${f x}(t) = c_1 {f w}_1(t) + c_2 {f w}_2(t) + c_3 e^{\lambda_3 t} {f v}_3.$$

The Eigenanalysis Method for Second Order Systems

Theorem 3 (Second Order Systems)

Let A be real and 3×3 with three negative eigenvalues $\lambda_1=-\omega_1^2$, $\lambda_2=-\omega_2^2$, $\lambda_3=-\omega_3^2$. Let the eigenpairs of A be listed as

$$(\lambda_1, \mathrm{v}_1), \ (\lambda_2, \mathrm{v}_2), \ (\lambda_3, \mathrm{v}_3).$$

Then the general solution of the second order system $\mathbf{x}''(t) = A\mathbf{x}(t)$ is

$$egin{aligned} \mathbf{x}(t) &= \left(a_1\cos\omega_1t + b_1rac{\sin\omega_1t}{\omega_1}
ight)\mathbf{v}_1 \ &+ \left(a_2\cos\omega_2t + b_2rac{\sin\omega_2t}{\omega_2}
ight)\mathbf{v}_2 \ &+ \left(a_3\cos\omega_3t + b_3rac{\sin\omega_3t}{\omega_3}
ight)\mathbf{v}_3 \end{aligned}$$

Vector-Matrix Form of the Solution of $\mathbf{x}' = A\mathbf{x}$

The solution of $\mathbf{x}' = A\mathbf{x}$ in the 3×3 case is written in vector-matrix form

$$\mathbf{x}(t) = \mathrm{aug}(\mathbf{v}_1, \mathbf{v}_2, \mathbf{v}_3) \left(egin{array}{ccc} e^{\lambda_1 t} & 0 & 0 \ 0 & e^{\lambda_2 t} & 0 \ 0 & 0 & e^{\lambda_3 t} \end{array}
ight) \left(egin{array}{c} c_1 \ c_2 \ c_3 \end{array}
ight).$$

This formula is normally used when the eigenpairs are real.

Complex Eigenvalues for a 2×2 System

When there is a complex conjugate pair of eigenvalues $\lambda_1 = \overline{\lambda}_2 = a + ib$, b > 0, then it is possible to extract a real solution x from the complex formula and report a real solution. The work can be organized more efficiently using the matrix product

$$\mathbf{x}(t) \ = \ e^{at} \operatorname{aug}(R\mathrm{e}(\mathbf{v}_1), I\mathrm{m}(\mathbf{v}_1)) \left(egin{array}{c} \cos bt & \sin bt \ -\sin bt & \cos bt \end{array}
ight) \left(egin{array}{c} c_1 \ c_2 \end{array}
ight).$$

Complex Eigenvalues for a 3×3 System

When there is a complex conjugate pair of eigenvalues $\lambda_1 = \overline{\lambda}_2 = a + ib$, b > 0, then a real solution x can be extracted from the complex formula to report a real solution. The work is organized using the matrix product

$$\mathbf{x}(t) \ = \ \mathrm{aug}(R\mathrm{e}(\mathrm{v}_1), I\mathrm{m}(\mathrm{v}_1), \mathrm{v}_3) \left(egin{array}{ccc} e^{at}\cos bt & e^{at}\sin bt & 0 \ -e^{at}\sin bt & e^{at}\cos bt & 0 \ 0 & 0 & e^{\lambda_3 t} \end{array}
ight) \left(egin{array}{c} c_1 \ c_2 \ c_3 \end{array}
ight).$$

Four Methods for Solving a 2 imes 2 System $\mathrm{u}' = A\mathrm{u}_-$

- 1. First-order method. If A is diagonal, then use growth-decay methods. If A is triangular, then use the linear integrating factor method.
- 2. Cayley-Hamilton-Ziebur method. If A is not diagonal, and $a_{12} \neq 0$, then $u_1(t)$ is a linear combination of the atoms constructed from the roots r of $\det(A rI) = 0$. Solution $u_2(t)$ is found from the system by solving for u_2 in terms of u_1 and u_1' .
- 3. Eigenanalysis method. Assume A has eigenpairs $(\lambda_1, \mathbf{v}_1)$, $(\lambda_2, \mathbf{v}_2)$ with \mathbf{v}_1 , \mathbf{v}_2 independent. Then $\mathbf{u}(t) = c_1 e^{\lambda_1 t} \mathbf{v}_1 + c_2 e^{\lambda_2 t} \mathbf{v}_2$.
- 4. Resolvent method. In Laplace notation, $\mathbf{u}(t) = L^{-1}\left((sI A)^{-1}\mathbf{u}(0)\right)$. The inverse of C = sI A is found from the formula $C^{-1} = \operatorname{adj}(C)/\det(C)$. Cramer's Rule can replace the matrix inversion method.

Four Methods for Solving an n imes n System $\mathrm{u}' = A\mathrm{u}$

- 1. First-order method. If A is diagonal, then use growth-decay methods. If A is triangular, then use the linear integrating factor method.
- 2. Cayley-Hamilton-Ziebur method. The solution $\mathbf{u}(t)$ is a linear combination of the atoms constructed from the roots r of $\det(A rI) = 0$,

$$\mathbf{u}(t) = (\operatorname{atom}_1)\vec{\mathbf{d}}_1 + \cdots + (\operatorname{atom}_n)\vec{\mathbf{d}}_n.$$

To solve for the constant vectors $\vec{\mathbf{d}}_j$, differentiate the formula n-1 times, then use $A^k\mathbf{u}(t)=\mathbf{u}^{(k+1)}(t)$ and set t=0, to obtain a system for $\vec{\mathbf{d}}_1,\ldots,\vec{\mathbf{d}}_n$.

- 3. Eigenanalysis method. Assume A has eigenpairs $(\lambda_1, \mathbf{v}_1), \ldots, (\lambda_n, \mathbf{v}_n)$ with $\mathbf{v}_1, \ldots, \mathbf{v}_n$ independent. Then $\mathbf{u}(t) = c_1 e^{\lambda_1 t} \mathbf{v}_1 + \cdots + c_n e^{\lambda_n t} \mathbf{v}_n$.
- 4. Resolvent method. In Laplace notation, $\mathbf{u}(t) = L^{-1}\left((sI A)^{-1}\mathbf{u}(0)\right)$. The inverse of C = sI A is found from the formula $C^{-1} = \operatorname{adj}(C)/\det(C)$. Cramer's Rule can replace the matrix inversion method.